

Calculate Linux - Bug # 84: Enumeration block devices by installer for grub.conf

|              |  |           |                     |
|--------------|--|-----------|---------------------|
| Status:      | New  | Priority: | High                |
| Author:      | Ð•Ð»ÐµÐ°Ñ•ÐµÐ¹ Ð¬Ñ,ÐµÐ¸Ð°  | Category: | Calculate Utilities |
| Created:     | 01/22/2010   | Assignee: | Mikhail Hiretsky    |
| Updated:     | 07/01/2011   | Due date: |                     |
| Subject:     | Enumeration block devices by installer for grub.conf   |           |                     |
| Description: | <p>At moment of the install system by calculate utility, the programm algorithm is wrong defines a block devices enumeration...</p> <p>I think because it get data from *fdisk* command output, but it`s give a incorrect result in some situations.</p> <p>h3. For example</p> <p>My server has a RAID Controller, who can support work together are two disk array.</p> <p>And I have this output fdisk:&lt;pre&gt;</p> <pre>fdisk -l   grep "/dev/sd" Disk /dev/sdb: 749.5 Gb, 749461307392 bytes /dev/sdb1          1      91116  731889238+  83  Linux Disk /dev/sda: 293.8 Gb, 293810995200 bytes /dev/sda1          1      12289  12583920   83  Linux /dev/sda2          12290    24578  12583936   83  Linux /dev/sda3          24579    32771   8389632   82  Linux swap / Solaris /dev/sda4          32772    280200  253367296  83  Linux</pre> <p>&lt;/pre&gt;</p> <p>You can see what fdisk define a /dev/sdb as first block disk device, itsn`t corectly.</p> <p>To verify this - I use udev sysfs and put next command:&lt;pre&gt;</p> <pre>ls -laF /sys/block/   grep sd lrwxrwxrwx  1 root root 0 Jun 23 02:11 sda -&gt; ../devices/pci0000:00/ ... /target0:0:0:0:0/block/sda/ lrwxrwxrwx  1 root root 0 Jun 23 02:11 sdb -&gt; ../devices/pci0000:00/ ... /target0:0:1:0:0/block/sdb/</pre> <p>&lt;/pre&gt;</p> <p>There we can see, how enumerate are block devices on PCI bus. :)</p> <p>But when I want install a system to /dev/sda2 slice, calculate utility make it correctltly, but in grub.conf, in the boot item, it write some like:&lt;pre&gt;</p> <pre>root (hd1,1)</pre> <p>&lt;/pre&gt;</p> <p>I think, what it a simple small bug, and not difficult for fixing ;-)</p> <p>Best regards, Alexey Shtepa.</p> |           |                     |

History

01/14/2011 10:07 am - Alexander Tratsevskiy

- Assignee set to Mikhail Hiretsky