

Calculate Linux - Feature # 21: minimal smb.conf (Win2k&Win7 - Work very good)

Status:	In Progress	Priority:	Low
Author:	rasperpodvipodvert none	Category:	Calculate Utilities
Created:	12/21/2009	Assignee:	
Updated:	01/31/2011	Due date:	
Subject:	minimal smb.conf (Win2k&Win7 - Work very good)		
Description:	<pre><pre> [global] max xmit = 64000 socket options = IPTOS_LOWDELAY TCP_NODELAY SO_SNDBUF=64000 SO_RCVBUF=64000 SO_KEEPAIVE workgroup = HOME server string = HOME-SRV security = share load printers = yes log file = /var/log/samba/log.%m max log size = 50 dns proxy = no restrict anonymous = no domain master = no logon home = \\%25N%25U logon path = \\%25N%25U\profile #===== Share Definitions ===== [homes] comment = Home Directories browseable = no read only = no [printers] comment = All Printers path = /var/spool/samba browseable = no guest ok = no printable = yes </pre></pre>		

History

12/25/2009 11:59 am - Alexander Tratsevskiy

- Target version deleted (4)

12/25/2009 12:56 pm - Alexander Tratsevskiy

- Project changed from en to Calculate Linux
- Category changed from Calculate Linux Desktop KDE to Calculate Linux Desktop KDE
- Status changed from New to In Progress
- Assignee deleted (Alexander Tratsevskiy)
- Start deleted (12/21/2009)

01/16/2010 10:32 pm - Ð•Ð²Ð³Ð¼Ð¹Ð, Ð¹ Ð² Ð³¼Ñ€Ð½•Ð³¼Ð²

I think, that is bad idea for calculate desktop series, but for Directory Server.

01/31/2011 11:13 am - Alexander Tratsevskiy

- Category changed from Calculate Linux Desktop KDE to Calculate Utilities
- Priority changed from Normal to Low

Files

smb.conf	7.3 KB	12/21/2009	rasperepodvipodvert none
----------	--------	------------	--------------------------